



About X5 Installation and Troubleshooting

X5 Leopard v1.00 for
Sony PSP™ (PlayStation®Portable) System Software v3.80+

Contents

Installation
Accessing X5
Uninstalling X5
Customization
Safari Search Engines
Unsupported Access
Troubleshooting

Installation

X5 requires approximately **8 MB** of free space for installation.*

- 1) Boot into Windows XP or Windows Vista.
- 2) Mount the Sony PSP™ (PlayStation®Portable) disk.
- 3) Right-click the X5.zip icon to extract the ZIP archive.
- 4) Drag the X5 folder to the **COMMON** directory.
- 5) Drag the X5.jpg image to the **PICTURE** directory.
- 6) Eject the Sony PSP™ (PlayStation®Portable) disk.

*KaotiK DesignZ is not responsible for any data loss that may occur from improper installation.

Accessing X5

Select **Internet Browser** from the XMB™ (XrossMediaBar) and type the following URL:
file:///PSP/COMMON/X5/index.html

Uninstalling X5

- 1) Boot into Windows XP or Windows Vista.
- 2) Mount the Sony PSP™ (PlayStation®Portable) disk.
- 3) Locate and remove the X5 folder from the **COMMON** directory.
- 4) Locate and remove the X5.jpg image from the **PICTURE** directory.
- 5) Eject the Sony PSP™ (PlayStation®Portable) disk.

Customization

Because alteration of a file can render it useless, HTML knowledge is recommended.

Adding a contact to Address Book

- 1) Locate the sidebar.html file from the **address** directory.
- 2) Find and remove <!-- and //--> for desired contact.
- 3) Locate the template.html file from the **contacts** directory.
- 4) Fill in desired information and rename file accordingly.
- 5) Repeat process for additional contacts.

Adding an event to iCal

- 1) Locate the desired year and month file from the **calendars** directory.
- 2) Find and remove <!-- and //--> for desired date.
- 3) Locate the template.html file from the **events** directory.
- 4) Fill in desired information, rename and place file accordingly.
- 5) Repeat process for additional events.

Adding a bookmark collection to Safari

- 1) Locate the sidebar.html file from the **safari** directory.
- 2) Find and remove <!-- and //--> for desired collection.
- 3) Locate the template.html file from the **collections** directory.
- 4) Fill in desired information and rename file accordingly.
- 5) Repeat process for additional bookmark collections.

Change short name in Finder

- 1) Locate the sidebar.html file from the **contents** directory.
- 2) Find and change **Home** to desired name.

Change “User” contact in Address Book

- 1) Locate the sidebar.html file from the **address** directory.
- 2) Find and change **User** to desired name.
- 3) Locate the 04.html file from the **contacts** directory.
- 4) Fill in desired information.

Change default site for Mail

- 1) Locate the mail.html file from the **safari** directory.
- 2) Find and change **http://www.me.com/mail/** to desired site.

Change default site for Safari

- 1) Locate the index.html file from the **safari** directory.
- 2) Find and change **http://livepage.apple.com/** to desired site.

Change default search engine for Safari

- 1) Locate the toolbar2.html file from the **safari** directory.
- 2) Find and change **http://www.google.com/hws/search?client=sce-psp-row&q=** and **Google** to desired search engine.

Safari Search Engines

Google (Default): <http://www.google.com/hws/search?client=sce-psp-row&q=>

MSN: <http://search.msn.com/results.aspx?q=>

Yahoo!: <http://search.yahoo.com/search?p=>

Unsupported Access

X5 requires **Safari v3.1+** for access via Windows XP or Windows Vista.*

- 1) Launch the Safari application.
- 2) Enable the Develop menu.
[Edit] > [Preferences...] > [Advanced] > [☒ Show Develop menu in the menu bar]
- 3) Change the User Agent.
[Develop] > [User Agent] > [Other...]
- 4) Type the following user agent string:
Mozilla/4.0 (PSP (PlayStation Portable); 2.00)
- 5) Locate and open the index.html file from the **x5** directory.

*X5 may look and perform differently than intended when accessed via Windows XP or Windows Vista.

Troubleshooting

The content cannot be displayed

- 1) Insure that the address is typed correctly. (See **Accessing X5**)
- 2) Insure that X5 was installed properly. (See **Installation**)

There is not enough memory

- 1) Close any additional tabs that may be open.
- 2) Set Cache Size to **Do Not Use**.
- 3) Set smaller size (KB) desktop picture.
- 4) Set Conserve Memory to **On**.

Content is not displayed properly

- 1) Set Images, Animation, JavaScript, and Flash to **On**.*
- 2) Set Text Size to **Normal**
- 3) Set Encoding to **Auto-Select**.
- 4) Set Display Mode to **Normal**.
- 5) Insure that X5 was installed properly. (See **Installation**)

Desktop picture is not displayed (Desktop is blue)

- 1) Insure that X5 was installed properly. (See **Installation**)

Documents, Downloads, iCal, iPhoto, and iTunes displays "Loading..."

- 1) Insure your network is configured properly.
- 2) Set JavaScript to **On**.

*Activation of the Flash®Player requires a network connection.

Note: KaotiK DesignZ is in no way affiliated with Apple Inc. X5 provides merely a simulation of Mac OS X. For a true Mac OS X experience, visit <http://store.apple.com/>.

Copyright © 2005–2008 KaotiK DesignZ. All rights reserved. Apple, the Apple logo, Finder, iCal, iPhoto, iTunes, Mac, the Mac logo, Mac OS, Macintosh, QuickTime, and Safari are trademarks of Apple Inc., registered in the U.S. and other countries. Google, and the Google logo are trademarks of Google Inc. PlayStation, the PlayStation logo, PSP, the PSP logo, Sony, XMB, the XMB logo, and XrossMediaBar are trademarks of Sony Corporation and Sony Computer Entertainment Inc. Also, Memory Stick, Memory Stick Duo, and Memory Stick Pro Duo are trademarks of the same company. Hosting provided by PSP 3D.